

# PIC KITCHEN Cookbook

Draft: May 30, 2008

## Processing steps to build ph5

**Overview:** This document outlines the steps to convert data from a seismic reflection or refraction experiment using the RefTek texan instruments to PASSCAL HDF5 (ph5) format. This example uses data from the Spears Ranch experiment in Oklahoma. Commands that are executed are shown in blue.

The steps required are to a) bring together the required files and information, in this case these include the raw data files, the TSP input files (geometry, das, and shot lists), and information about the experiment from the PIs, b) read this information into the ph5 file, c) verify the ph5 file, d) generate two text files, data\_description.txt, and data\_request\_key.txt (used to generate the DMC's web form), and e) transmit the ph5 file to the DMC.

The method described here should be considered preliminary as it is likely to be greatly simplified as more experience with its use is gained.

**1)** Bring together the needed input files, raw TRD files, das file, shot file, geometry file (TSP input files). In addition, get information about the experiment, such as PI's names and institutions, the purpose of the experiment, the size and depth of the shots, and the type of geophones used.

**2)** Run tsp2dep to convert the TSP input files into a dep file as produced by rawmeet. This step is not necessary on PASSCAL run experiments using the rawmeet program.

```
usage: tsp2dep -u tsp_utm_file -d tsp_das_file -s tsp_shot_file
```

Convert TSP input files to a dep file. Writes to stdout.

options:

```
-h, --help          show this help message and exit
-u tsp_utm_file, --utm=tsp_utm_file
                    A TSP geometry file. "station, northing, easting,
                    elevation"
-d tsp_das_file, --das=tsp_das_file
                    A TSP DAS file. "station, das_number"
-s tsp_shot_file, --shot=tsp_shot_file
                    A TSP shot file. "year, doy, hr, mn, sc, station,
                    length"
-D
```

```
flow@localhost% tsp2dep -s spears.shot -u spears.utm -d spears.das > SOAD.dep
```

**3)** Create a kef (Kitchen Exchange Format) file to describe the experiment. Each tabbed in section of the kef file describes, in key value pairs, a line in the preceding table line. In the following example a single line of the /Experiment\_g/Experiment\_t is modified. See example below.

```
# Start of file SOAD-experiment.kef
/Experiment_g/Experiment_t
    PIs_s = Dr. G. Randy Keller, Dr. Steven H. Harder, Dr. Kate C. Miller,\
    Dr. Catherine M. Snelson
    institutions_s = University of Oklahoma, University of Texas, El Paso,\
    University of Nevada at Las Vegas
    longname_s = Spears Ranch Seismic Experiment Survey
    nickname_s = SOAD
    north_west_corner/X/units_s = degrees
    north_west_corner/X/value_d = -96.654163
    north_west_corner/Y/units_s = degrees
    north_west_corner/Y/value_d = 34.452259
    north_west_corner/Z/units_s = meters
    north_west_corner/Z/value_d = 315
    north_west_corner/coordinate_system_s = mercator
    north_west_corner/description_s = Estimated elevation
    north_west_corner/ellipsoid_s = WGS84
    north_west_corner/projection_s = None
    south_east_corner/X/units_s = degrees
    south_east_corner/X/value_d = -96.645916
    south_east_corner/Y/units_s = degrees
    south_east_corner/Y/value_d = 34.435873
    south_east_corner/Z/units_s = meters
    south_east_corner/Z/value_d = 315
    south_east_corner/coordinate_system_s = mercator
    south_east_corner/description_s = Estimated elevation
    south_east_corner/ellipsoid_s = WGS84
    south_east_corner/projection_s = None
    summary_paragraph_s = A 2-D seismic reflection experiment on the Spears Ranch\
    in Oklahoma. The purpose is to image the Arbuckle-Simpson aquifer.
    time_stamp/ascii_s = Thu Jun 28 14:58:00 2007
    time_stamp/epoch_l = 1183064280
    time_stamp/micro_seconds_i = 0
    time_stamp/type_s = "BOTH"
# End of file
```

To update the line keyed on time\_stamp/epoch\_l substitute the line:

/Experiment\_g/Experiment\_t:Update:time\_stamp/epoch\_l

To delete the first line containing time\_stamp/epoch\_l with the value in the kef file substitute the line:

/Experiment\_g/Experiment\_t>Delete:time\_stamp/epoch\_l

Warning: You can not delete a line from the table if it is the only line.

**4) Run initialize-ph5 to create an empty ph5 file for the experiment processing. See kef file above.**


usage: initialize-ph5 [--help]--kef=kef\_file --nickname=output\_file

Program to initialize PH5 file at start of experiment. The kef file should contain information for experiment table /Experiment\_g/Experiment\_t.

options:

```
-h, --help          show this help message and exit
-n output_file, --nickname=output_file
                    Experiment nickname.
-k kef_file, --kef=kef_file
                    Kitchen Exchange Format file containing experiment
                    info.
```

```
flow@localhost% initialize-ph5 -n SOAD -k SOAD-experiment.kef
```



*Illustration 1: ph5 file tree as viewed in hdfview*

**5)** Process the raw TRD files and the dep file into the ph5 file using 125a2ph5. The file “SOAD-file-list.txt” contains a list of the raw files, the file SOAD.dep contains much of the meta-data for the experiment in dep (rawmeet) format. For an experiment using the rawmeet program the dep file would contain all of the meta-data.

```
usage: 125a2ph5 [--help][--dep dep_file][--kef kef_file][--raw raw_file | --file
file_list_file] --nickname output_file_prefix
```

Read the raw texan files and optionally a kef file into ph5 format.

options:

```
-h, --help          show this help message and exit
-r raw_file, --raw=raw_file
                    RT-125(a) texan raw file
-f file_list_file, --file=file_list_file
                    File containing list of RT-125(a) raw file names.
-n output_file_prefix, --nickname=output_file_prefix
                    The ph5 file prefix (experiment nick name).
-k kef_file, --kef=kef_file
                    Kitchen Exchange Format file.
-d dep_file, --dep=dep_file
                    Rawmeet dep file.
```

This program takes as input a file containing a list of raw TRD files and the dep file created above.


```
flow@localhost% head SOAD-file-list.txt
```

```
RAW/I2631RAW.TRD
RAW/I2810RAW.TRD
RAW/I1554RAW.TRD
...
RAW/I2496RAW.TRD
```

```
flow@localhost% head SOAD.dep
```

```
# tsp2dep Version: 2007.177 dep Version: 0007.107 TSP Version: 3.1 Run: Tue Jun 26 09:16:46
2007
SHOT;1000;1000;1;N34.450543;W96.651557;306.116000;2007:151:15:01:0;;;;;;;;;
SHOT;1002;1002;1;N34.450183;W96.651565;307.655000;2007:151:15:07:0;;;;;;;;;
...
RECV;12839;2036;2;texan;1;;N34.448596;W96.645643;308.465000;;;;;;;;;
```

```
flow@localhost% 125a2ph5 -n SOAD -d SOAD.dep -f SOAD-file-list.txt
```



*Illustration 2: Receivers group tree*

**6)** Calculate offsets and insert them into the ph5 file using geod2kef then kef2ph5. This can only be done if geometry info was included in the dep file.

```
usage: geod2kef --nickname output_file_prefix [--path][-h][--listellipsoids][--listunits][-U units][-E ellipsoid]
```

Read locations and calculate offsets from events to receivers. Produce kef file to populate ph5 file.

options:

-h, --help	show this help message and exit
-n output_file_prefix, --nickname=output_file_prefix	The ph5 file prefix (experiment nick name).
-p output_file_path, --path=output_file_path	Path to directory containing ph5 files. Defaults to current directory
-U output_units	Units to output offsets in. (Use -u to get list of acceptable units.) Default == 'm' (meters)
-E calculation_ellipsoid	Ellipsoid to use. (Use -e to get a list of acceptable ellipsoids.) Default == 'WGS84'
-e, --listellipsoids	List available ellipsoids.
-u, --listunits	List all available output units.

Geometry is in geodetic units and meters, which are the defaults for geod2kef, rawmeet, as well as accommodated in ph5.

```
flow@localhost% geod2kef -n SOAD > SOAD-Offset_t.kef
```

Note: geod2kef writes to stdout.

Next insert the offsets into the ph5 file using kef2ph5.

```
usage: kef2ph5 --kef kef_file --nickname ph5_file_prefix [--path path]
```

Update a ph5 file from a kef file.

options:

```
-h, --help          show this help message and exit
-n OUTFILE, --nickname=OUTFILE
                    The ph5 file prefix (experiment nickname).
-k KEFFILE, --kef=KEFFILE
                    Kitchen Exchange Format file.
-p PATH, --path=PATH Path to directory where ph5 files are stored.
-c, --check         Show what will be done but don't do it!
```

```
flow@localhost% kef2ph5 -n SOAD -k SOAD-Offset_t.kef -c
```

If no errors, then run:

```
flow@localhost% kef2ph5 -n SOAD -k SOAD-Offset_t.kef
```

azimuth.value_f	azimuth.units_s	event_id_s	offset.value_d	offset.units_s	receiver_id_s
0.0	degrees	1000	0.0	m	1000
-179.73778	degrees	1000	20.079	m	1001
-178.94537	degrees	1000	39.942	m	1002
-178.8575	degrees	1000	59.914	m	1003
-178.68362	degrees	1000	80.002	m	1004
-178.7359	degrees	1000	99.973	m	1005
-178.72571	degrees	1000	119.835	m	1006
-178.49594	degrees	1000	140.043	m	1007
-178.5181	degrees	1000	159.904	m	1008
-178.38997	degrees	1000	179.889	m	1009

*Illustration 3: Offset table*

**7) Run time-kef-gen to generate time corrections and then kef2ph5 to insert them into the ph5 file.**

```
usage: time-kef-gen --nickname ph5-file-prefix [-p path]
```

Generates a kef file to populate Time\_t from SOH\_A\_.

options:

```
-h, --help          show this help message and exit
-n ph5_file_prefix, --nickname=ph5_file_prefix
                    The ph5 file prefix (experiment nickname).
-p ph5_path, --path=ph5_path
                    Path to ph5 files. Defaults to current directory.
```

**8)** Since the input files were in TSP format and not dep format some of the information is not in the ph5 file yet. This is easy to add. The example below adds information about the sensors used. First dump a table to kef format, then edit the kef file and use it to update the ph5 file.

```
usage: tabletokef --nickname ph5-file-prefix options
```

Dump a table to a kef file.

options:

```
-h, --help          show this help message and exit
-n ph5_file_prefix, --nickname=ph5_file_prefix
                    The ph5 file prefix (experiment nickname).
-p ph5_path, --path=ph5_path
                    Path to ph5 files. Defaults to current directory.
-d
-E, --Experiment_t  Dump /Experiment_g/Experiment_t to a kef file.
-S, --Sort_t        Dump /Experiment_g/Sorts_g/Sort_t to a kef file.
-O, --Offset_t      Dump /Experiment_g/Sort_g/Offset_t to a kef file.
-V, --Event_t       Dump /Experiment_g/Sorts_g/Event_t to a kef file.
-A n, --Array_t=n   Dump /Experiment_g/Sorts_g/Array_t[n] to a kef file.
-R, --Response_t    Dump /Experiment_g/Responses_g/Response_t to a kef
                    file.
-P, --Report_t      Dump /Experiment_g/Reports_g/Report_t to a kef file.
-C das, --Receiver_t=das
                    Dump /Experiment_g/Receivers_g/Das_g[das]/Receiver_t
                    to a kef file.
-D das, --Das_t=das Dump /Experiment_g/Receivers_g/Das_g[das]/Das_t to a
                    kef file.
```

(Note: The -C and -D options do not work with current file organization. A known bug.)

Get a copy of /Experiment\_g/Sorts\_g/Array\_t\_001.

```
flow@localhost% tabletokef -n SOAD -A 1 > SOAD-Array_t_001.kef
```

Now edit SOAD-Array\_t\_001.kef, using the editor of your choice, and replace each instance of /Experiment\_g/Sorts\_g/Array\_t\_001

with

/Experiment\_g/Sorts\_g/Array\_t\_001:Update:id\_s

and

sensor/model\_s =

with

sensor/model\_s = 4.5Hz Vertical

```
# Start of file
#
# Wed Jun 27 13:49:26 2007 ph5 version: 2007.121 Bleeding
#
# Table row 1
/Experiment_g/Sorts_g/Array_t_001:Update:id_s
  id_s = 1000
  location/Y/value_d = 34.450543
  location/Y/units_s = degrees
  location/X/value_d = -96.651557
  location/X/units_s = degrees
  location/Z/value_d = 306.116
  location/Z/units_s = meters
  location/coordinate_system_s =
  location/projection_s =
  location/ellipsoid_s =
  location/description_s =
  deploy_time/ascii_s =
  deploy_time/epoch_l = -1
  deploy_time/micro_seconds_i = 0
  deploy_time/type_s =
  pickup_time/ascii_s =
  pickup_time/epoch_l = -1
  pickup_time/micro_seconds_i = 0
  pickup_time/type_s =
  das/serial_number_s = 11642
  das/model_s = texan rt125a
  das/manufacturer_s = RefTek
  das/notes_s =
  sensor/serial_number_s =
  sensor/model_s = 4.5Hz Vertical
  sensor/manufacturer_s = GeoSpace Corp.
  sensor/notes_s =
  description_s =
  channel_number_i = 1
# Table row 2
/Experiment_g/Sorts_g/Array_t_001:Update:id_s
  id_s = 1001
  location/Y/value_d = 34.450362
  location/Y/units_s = degrees
```

```

...

# Table row 77
/Experiment_g/Sorts_g/Array_t_001:Update:id_s
    id_s = 1076
    location/Y/value_d = 34.43691
    location/Y/units_s = degrees

...

# End of file

```

Next run kef2ph5. This will update /Experiment\_g/Sorts\_g/Array\_t\_001, keying the update on the value of id\_s. This is done by the line /Experiment\_g/Sorts\_g/Array\_t\_001:Update:id\_s shown above.

```

flow@localhost% kef2ph5 -n SOAD -k SOAD-Array_t_001.kef -c
if no errors:
flow@localhost% kef2ph5 -n SOAD -k SOAD-Array_t_001.kef

```

Note: /Experiment\_g/Sorts\_g/Event\_t should also be updated to contain information about the size and depth of the shots.

**9) Populate /Experiment\_g/Sorts\_g/Sort\_t to describe all of the shot windows by running sort-kef-gen.**

```

usage: sort-kef-gen --nickname ph5-file-prefix --serial-number DAS-SN [--path path-
to-ph5-files]

```

Generate a kef file to populate Sort\_t.

```

options:
-h, --help                show this help message and exit
-n ph5_file_prefix, --nickname=ph5_file_prefix
                           The ph5 file prefix (experiment nickname).
-p ph5_path, --path=ph5_path
                           Path to ph5 files. Defaults to current directory.
-s sn, --serial-number=sn
                           DAS to use to get windows.
-d

```

Use hdfview to find an instrument that recorded all of the shot windows. In this case DAS 11519.

```

flow@localhost% sort-kef-gen -n SOAD -s 11519 > SOAD-Sort_t.kef

```

```

flow@localhost% kef2ph5 -n SOAD -k SOAD-Sort_t.kef -c
if no error
flow@localhost% kef2ph5 -n SOAD -k SOAD-Sort_t.kef

```

Now generate a small kef file to delete the first two lines of the Sort\_t table that were inserted there by 125a2ph5 as place holders.



**10)** Create `data_request_key.txt` and `data_description.txt`. This is done by running `report-gen`. You will need to edit the resulting `data_description.txt` for formatting. These two files are used by the DMC to generate the web form for this data set.

```
usage: report-gen --nickname=ph5-file-prefix options
```

Generate `data_description.txt` and/or `data_request_key.txt`.

options:

```
-h, --help          show this help message and exit
-n ph5_file_prefix, --nickname=ph5_file_prefix
                    The ph5 file prefix (experiment nickname).
-p ph5_path, --path=ph5_path
                    Path to ph5 files. Defaults to current directory.
-k, --key           Write data_request_key.txt.
-d, --description  Write data_description.txt.
--bug
```

```
flow@localhost% report-gen -n SOAD -k -d
```

**11)** Insert `data_description.txt`, and `data_request_key.txt` into `SOAD.ph5` using `report2ph5`.

```
usage: report2ph5 --file report-file --kef kef-file --nickname experiment-nickname
[--path path-to-kef-file]
```

Load a report (pdf) into a ph5 file.

options:

```
-h, --help          show this help message and exit
-f REPORT_FILE, --file=REPORT_FILE
                    The file containing the report, (pdf, doc, ps, etc.).
-k KEF_FILE, --kef=KEF_FILE
                    Kef file describing row in Report_t for the report.
-n NICKNAME, --nickname=NICKNAME
                    Experiment nickname.
-p PATH, --path=PATH Path to where ph5 files are stored
```

```
flow@localhost% cat SOAD-desc.kef
/Experiment_g/Reports_g/Report_t
    array_name_a = data_description
    description_s = Text file describing the experiment layout.
    format_s = TXT
    title_s = data_description
flow@localhost% cat SOAD-key.kef
/Experiment_g/Reports_g/Report_t
    array_name_a = data_request_key
    description_s = Text file of sort request keys.
    format_s = TXT
    title_s = data_request_key
```

```
flow@localhost% report2ph5 -k SOAD-desc.kef -f data_description.txt
flow@localhost% report2ph5 -k SOAD-key.kef -f data_request_key.txt
```

**12)** At this point run hdfview to verify the values in SOAD.ph5, and run ph5toseg to generate a test SEG-Y gather. Be sure to review the log generated by ph5tpseg.

```
usage: ph5toseg --nickname ph5-file-prefix [options]
```

Convert ph5 file to SEG format. (Presently only SEG-Y and PASSCAL SEG-Y trace files)

options:

```
-h, --help          show this help message and exit
-n ph5_file_prefix, --nickname=ph5_file_prefix
                    The ph5 file prefix (experiment nickname).
-p ph5_path, --path=ph5_path
                    Path to ph5 files. Defaults to current directory.
-s sort_table_line, --sorttableline=sort_table_line
                    Sort table line number.
-o gatherpath, --outpath=gatherpath
                    Directory to write gathers and reports to.
-d
-P, --passcal-segy  Generate PASSCAL SEG-Y trace files.
```

```
flow@localhost% mkdir GATHERS; ph5toseg -n SOAD -o ./GATHERS -s 2
```

**13)** Transmit SOAD.ph5 to bob.iris.washington.edu:/hdf5-data/incoming/SOAD (should use report number) along with data\_description.txt and data\_request\_key.txt. The two text files are best extracted from the ph5 file at the DMC using dumpreports.

```
usage: dumpreports --nickname ph5-file-prefix [--path path-to-ph5-files]
```

Dump reports from a ph5 file

options:

```
-h, --help          show this help message and exit
-n ph5_file_prefix, --nickname=ph5_file_prefix
                    The ph5 file prefix (experiment nickname).
-p ph5_path, --path=ph5_path
                    Path to ph5 files. Defaults to current directory.
```

```
[5] <bob:PIC>(SOAD) \pwd
/hdf5-data/incoming/SOAD
[6] <bob:PIC>(SOAD) dumpreports -n SOAD
File: data_description.TXT
Description: Text file describing the experiment layout.
Write: data_description.TXT? (y/n) y
File: data_request_key.TXT
Description: Text file of sort request keys.
Write: data_request_key.TXT? (y/n) y
File: Spears_Report.PDF
Description: Report generated for the PI supplied gather.
Write: Spears_Report.PDF? (y/n) n
```

## Quick Check List

Initialize ph5 file and fill Experiment\_t and Experiment\_g/Receivers\_g/Receiver\_t.

```
initialize-ph5 -n XX-XXX -k Experiment_t.kef
```

Process raw-data and meta-data into ph5 file.

```
125a2ph5 -n XX-XXX -d XX-XXX.dep -f XX-XXX.files.txt
```

Populate Offset\_t with offsets.

```
geod2kef -n XX-XXX > Offset_t.kef  
kef2ph5 -n XX-XXX -k Offset_t.kef
```

Populate Time\_t with timing information.

```
time-kef-gen -n XX-XXX > Time_t.kef  
kef2ph5 -n XX-XX -k Time_t.kef
```

Populate Sort\_t with recording window information.

```
sort-kef-gen -n XX-XXX -s nnnnn > Sort_t.kef  
kef2ph5 -n XX-XXX -k Sort_t.kef  
(Delete any NULL lines at start of table, one for each array)
```

Generate data\_request\_key.txt and data\_description.txt and insert them into the ph5 file.

```
report-gen -n XX-XXX -k  
report-gen -n XX-XXX -d  
(Hand edit both resulting files)  
report2ph5 -n XX-XXX -f data_request_key.txt  
report2ph5 -n XX-XXX -f data_description.txt
```

Load default Receiver\_t information.

```
kef2ph5 -n XX-XXX -k Receiver_t.kef -c  
(if no errors)  
kef2ph5 -n XX-XXX -k Receiver_t.kef
```

Verify ph5 file using hdfview and generate test gathers.

```
ph5toseg -n XX-XXX -s nn  
(The value for the -s option comes from data_request_key.txt)
```

PH5 TABLE KEYS - Feb 03, 2007

```

/Experiment_g/Experiment_t
    nickname_s
    longname_s
    PIs_s
    institutions_s
    north_west_corner/X/value_d
    north_west_corner/X/units_s
    north_west_corner/Y/value_d
    north_west_corner/Y/units_s
    north_west_corner/Z/value_d
    north_west_corner/Z/units_s
    north_west_corner/coordinate_system_s
    north_west_corner/projection_s
    north_west_corner/ellipsoid_s
    north_west_corner/description_s
    south_east_corner/X/value_d
    south_east_corner/X/units_s
    south_east_corner/Y/value_d
    south_east_corner/Y/units_s
    south_east_corner/Z/value_d
    south_east_corner/Z/units_s
    south_east_corner/coordinate_system_s
    south_east_corner/projection_s
    south_east_corner/ellipsoid_s
    south_east_corner/description_s
    summary_paragraph_s
    time_stamp/ascii_s
    time_stamp/epoch_l
    time_stamp/micro_seconds_i
    time_stamp/type_e
/Experiment_g/Receivers_g/Das_g_[sn]/Das_t
    array_name_data_a
    channel_number_i
    event_number_i
    raw_file_name_s
    receiver_table_n_i
    sample_rate_i
    stream_number_i
    time/ascii_s
    time/epoch_l
    time/micro_seconds_i
    time/type_e

```

```
/Experiment_g/Receivers_g/Das_g_[sn]/Receiver_t
orientation/azimuth/value_f
orientation/azimuth/units_s
orientation/dip/value_f
orientation/dip/units_s
orientation/description_s
/Experiment_g/Sorts_g/Sort_t
array_t_name_s
array_name_s
start_time/ascii_s
start_time/epoch_l
start_time/micro_seconds_i
start_time/type_e
end_time/ascii_s
end_time/epoch_l
end_time/micro_seconds_i
end_time/type_e
description_s
time_stamp/ascii_s
time_stamp/epoch_l
time_stamp/micro_seconds_i
time_stamp/type_e
```

```
/Experiment_g/Sorts_g/Array_t_[nnn]
  id_s
  location/X/value_d
  location/X/units_s
  location/Y/value_d
  location/Y/units_s
  location/Z/value_d
  location/Z/units_s
  location/coordinate_system_s
  location/projection_s
  location/ellipsoid_s
  location/description_s
  deploy_time/ascii_s
  deploy_time/epoch_l
  deploy_time/micro_seconds_i
  deploy_time/type_e
  pickup_time/ascii_s
  pickup_time/epoch_l
  pickup_time/micro_seconds_i
  pickup_time/type_e
  das/serial_number_s
  das/model_s
  das/manufacturer_s
  das/notes_s
  sensor/serial_number_s
  sensor/model_s
  sensor/manufacturer_s
  sensor/notes_s
  description_s
/Experiment_g/Sorts_g/Offset_t
  azimuth/value_f
  azimuth/units_s
  event_id_s
  offset/value_d
  offset/units_s
  receiver_id_s
```

```
/Experiment_g/Sorts_g/Event_t
  id_s
  location/X/value_d
  location/X/units_s
  location/Y/value_d
  location/Y/units_s
  location/Z/value_d
  location/Z/units_s
  location/coordinate_system_s
  location/projection_s
  location/ellipsoid_s
  location/description_s
  time/ascii_s
  time/epoch_l
  time/micro_seconds_i
  time/type_e
  size/value_d
  size/units_s
  depth/value_d
  depth/units_s
  description_s
/Experiment_g/Reports_g/Report_t
  array_name_a
  description_s
  format_s
  title_s
```

## Meta-Data, Data Required

### Shot/Source information:

- time of shot/source
- id of shot/source
- latitude of shot/source
- longitude of shot/source
- elevation of shot/source
- size of shot in kg or magnitude of source
- depth below surface of shot/source
- vibrator sweep information (if applicable)
- comments (if applicable)

### Receiver/Station information:

- id of station
- serial number of receiver
- manufacturer and model of receiver
- type of sensor attached (including response info if applicable)
- latitude of station
- longitude of station
- elevation of station
- comments (if applicable)

### General information about experiment:

- principal investigators
- institutions
- experiment name
- experiment nickname
- paragraph describing purpose of experiment
- paragraph describing layout of instruments

### Raw data files:

- raw data files